

General

Change Windows Evaluation Licenses

If the Eval version is all you have access to you can totally convert it to the correct version and apply. Use this method to change eval to VLSC License

Server 2019 Activation Error: Run " slui.exe 0x2a 0xC004F069 " to display the error text

This can be worked around by using two DISM commands. /t /h /h

Open an elevated command prompt, and type (or copy) DISM.exe /Online /Get-TargetEditions

Then enter DISM /online /Set-Edition:ServerStandard /ProductKey:ENTER-YOUR-SERIAL-FROM-TABLE /AcceptEula (use key from below table if this is a MAK/Volume license key) /t /h /h

It may get stuck on the 10% mark for a few

Use one of the below keys first: /t /h /h

OR

For Retail /h

To activate your Windows Server:

1. Enter key via GUI or run the command: slmgr.vbs /ipk XXXXX-XXXXX-XXXXX-XXXXX-XXXXX /t /h /h

To get the available editions:

1. Open an elevated command prompt.
2. Run the following command: DISM.exe /Online /Get-TargetEditions

To set your Windows Server to a higher edition:

1. Run the following command: DISM.exe /online /Set-Edition:ServerStandard /ProductKey:XXXXX-XXXXX-XXXXX-XXXXX-XXXXX /AcceptEula

(Use key from table below if this is a MAK/Volume license key) /t /h /h

And a link to the resource I use Here are the notes to get an MAK key working on an evaluation ISO. /t /h

<https://docs.microsoft.com/en-us/answers/questions/58587/windows-server-2019-activation-from-evaluat...>

Windows Server 2022 - KMS Client Setup Key

Windows Server 2022 Datacenter

- WX4NM-KYWYW-QJJR4-XV3QB-6VM33 /t /h /h

Windows Server 2022 Standard

- VDYBN-27WPP-V4HQT-9VMD4-VMK7H

Windows Server 2019 - KMS Client Setup Key /t /h /h

Windows Server 2019 Datacenter

- WMDGN-G9PQG-XVVXX-R3X43-63DFG

Windows Server 2019 Standard

- N69G4-B89J2-4G8F4-WWYCC-J464C /t /h /h

General

Windows Server 2019 Essentials
- WVDHN-86M7X-466P6-VHXV7-YY726

Windows Server 2016 - KMS Client Setup Key /k /h /h

Windows Server 2016 Datacenter
- CB7KF-BWN84-R7R2Y-793K2-8XDDG

Windows Server 2016 Standard
- WC2BQ-8NRM3-FDDYY-2BFGV-KHKQY /k /h /h

Windows Server 2016 Essentials
- JCKRF-N37P4-C2D82-9YXRT-4M63B

Windows Server 2019

Product GVLK

Windows Server 2019 Datacenter WMDGN-G9PQG-XVVXX-R3X43-63DFG

Windows Server 2019 Standard N69G4-B89J2-4G8F4-WWYCC-J464C

Windows Server 2019 Essentials WVDHN-86M7X-466P6-VHXV7-YY726

Windows Server 2019 Azure Core FDNH6-VW9RW-BXPJ7-4XTYG-239TB

Windows Server 2019 Datacenter Semi-Annual Channel (v.1809) 6NMRW-2C8FM-D24W7-TQWMY-CWH2D

Windows Server 2019 Standard Semi-Annual Channel (v.1809) N2KJX-J94YW-TQVFB-DG9YT-724CC

Windows Server 2019 ARM64 GRFBW-QNDC4-6QBHG-CCK3B-2PR88

Windows Server 2016

Product GVLK

Windows Server 2016 Standard Semi-Annual Channel (v.1803) PTXN8-JFHJM-4WC78-MPCBR-9W4KR

Windows Server 2016 Datacenter Semi-Annual Channel (v.1803) 2HXDN-KRXHB-GPYC7-YCKFJ-7FVDG

Windows Server 2016 Datacenter Semi-Annual Channel (v.1709) 6Y6KB-N82V8-D8CQV-23MJW-BWTG6

Windows Server 2016 Standard Semi-Annual Channel (v.1709) DPCNP-XQFKJ-BJF7R-FRC8D-GF6G4

Windows Server 2016 ARM64 K9FYF-G6NCK-73M32-XMVPY-F9DRR

Windows Server 2016 Datacenter CB7KF-BWN84-R7R2Y-793K2-8XDDG

Windows Server 2016 Standard WC2BQ-8NRM3-FDDYY-2BFGV-KHKQY

Windows Server 2016 Essentials JCKRF-N37P4-C2D82-9YXRT-4M63B

Windows Server 2016 Cloud Storage QN4C6-GBJD2-FB422-GHWJK-GJG2R

Windows Server 2016 Azure Core VP34G-4NPPG-79JTQ-864T4-R3MQX

WNCYY-GFBH2-M4WTT-XQ2FP-PG2K9

General

Finally reboot and enter your purchased key:

- Enter key via GUI

or

- slmgr.vbs /ipk <your product key>

- slmgr.vbs /ato

μ μ ::

: #1005

:: Kosmas

μ : 2026-05-11 14:19